

UWB Qorvo Tools guide

Qorvo

Release 1.0.2

Contents

1

UWB Qorvo Tools

1

1.1

Root Folder Organization

2

1.2

Prerequisites

3

1.3

Quick Start

4

1.4

Manual: About communicating with a DUT

7

1.5

Manual: about configuring your DUT

8

2

scripts

9

2.1

Scripts Introduction

9

2.2

device

10

2.3

fira

17

2.4

qorvo

32

2.5

utils

35

1 UWB Qorvo Tools

Welcome to the 'UWB Qorvo Tools' (UQT) Reference Guide. This guide is designed to help you navigate and utilize the various tools provided by Qorvo for operating Ultra-Wideband (UWB) devices through the UCI (UWB Communication Interface).

Warning: These tools are delivered by Qorvo as UCI examples on an as-is basis and are not optimized nor meant to be used as an end product.

1.1 Root Folder Organization

Here is the core structure and key components of the UQT library. Less critical files and directories have been omitted.

```

uwb-qorvo-tools
├── README.md
├── pyproject.toml
├── lib
│   ├── uqt-utils
│   └── uwb-uci
├── scripts
│   ├── <functionality_1>
│   │   ├── <example_1>
│   │   │   ├── <example_1_main.py>
│   │   │   ├── <example_1_helper.py>
│   │   │   └── ...
│   │   └── ...
│   └── ...
└── ...

↳ for functionality 1.
    ├── README.md
    ├── <example_2>
    ├── ...
    └── README.md

↳ functionalities.
    ├── <functionality_2>
    └── ...

<-- UQT Introduction
<-- UQT Project configuration file.
<-- Library folder.
<-- Helpers for main scripts.
<-- UCI transport layer libraries.
<-- Script folder divided into "chapters".
<-- A "chapter" represents functionality 1.
<-- Example 1 for functionality 1.
<-- Entrance point for example 1 for functionality 1.
<-- Helper script for example 1 for functionality 1.
<-- Other scripts and assets needed for for example 1.
<-- Documentation for example 1 for functionality 1.
<-- Example 2 for functionality 1.
<-- Other examples for functionality 1.
<-- Generic documentation for functionality 1.
<-- A "chapter" represents functionality 2.
<-- Other "chapters" represent further

```

1.2 Prerequisites

- Installed python 3.10
- Installed pip 21.3 or greater

1.2.1 Python

You may download Python 3.10 from [official web page](#) or install it using an appropriate package manager.

In Linux you may install python using apt:

```
sudo apt-get install python3.10
```

In Windows PowerShell you may install python using chocolatey:

```
choco install python310 -y
```

1.2.2 PIP upgrade

You may upgrade pip to a required version by executing:

```
pip install pip>=21.3 --upgrade
```

1.2.3 Other specific set-ups

1.2.3.1 Linux

Some scripts relies on PySide library. It seems that on Ubuntu 22.04, the PySide environment installed by pip is missing some extra library. If you got the below run-time error:

```
qt.qpa.plugin: Could not load the Qt platform plugin "xcb" in "" even though it was found"
```

You must install the library below:

```
sudo apt install libxcb-xinerama0
```

1.3 Quick Start

1.3.1 Install UQT

After you have installed the prerequisites mentioned above, you can proceed with the installation of UQT. There are two types of installations: editable and non-editable. The non-editable installation is the default option and is recommended for most users. However, if you need to make modifications to the UQT codebase, you should use the editable installation.

1.3.1.1 Non-Editable Installation

To perform a non-editable installation of UQT, follow these steps:

1.3.1.1.1 Linux

```
cd uwb-qorvo-tools
python -m venv .venv
source .venv/bin/activate
pip install .
```

1.3.1.1.2 Windows PowerShell

```
cd uwb-qorvo-tools
python -m venv .venv
.\.venv\Scripts\activate.ps1
pip install .
```

1.3.1.2 Editable Installation

To perform an editable installation of UQT, follow these steps:

1.3.1.2.1 Linux

```
cd uwb-qorvo-tools
python -m venv .venv
source .venv/bin/activate
pip install -e .
pip install -e lib/uqt-utils/
pip install -e lib/uwb-uci/
```

1.3.1.2.2 Windows PowerShell

```
cd uwb-qorvo-tools
python -m venv .venv
.\.venv\Scripts\activate.ps1
pip install -e .
pip install -e lib/uqt-utils/
pip install -e lib/uwb-uci/
```

Note: The order of package installation matters!. When performing an editable installation, it is important to install the packages in the following order: UQT, uqt-utils, and uwb-uci. This ensures that any changes made in the dependencies are properly reflected in the main project. When installing the main project in editable mode using `pip install -e .`, it is crucial to manually install the dependencies in the correct order to ensure that any changes made in the dependencies are properly reflected in the main project.

1.3.2 Executing programs

If UQT is installed within a virtual environment, you must activate the virtual environment before executing scripts. If UQT is installed globally, you can skip this step.

To activate the virtual environment, follow the instructions below:

Linux

```
cd uwb-qorvo-tools
source .venv/bin/activate
```

Windows PowerShell

```
cd uwb-qorvo-tools
.\.venv\Scripts\activate.ps1
```

Warning On Windows recommended to use shell is PowerShell. Other shell like cmd, Git Bash, etc. may require activation of the virtual environment with other activation scripts.

After the virtual environment is activated you may use Python scripts as other regular Python scripts:

```
python /path/to/script1.py <arg1> <arg2> <...>
python /path/to/script2.py <arg1> <arg2> <...>
```

The second option is using entry points. In this case, an explicit call to python is not needed:

```
<entry_point1> <arg1> <arg2> <...>
<entry_point2> <arg1> <arg2> <...>
```

1.3.3 How to check all possible entry points

```
uqt_ls
-> <script_name_1>          One line description of <script_name_1>
-> <script_name_2>          One line description of <script_name_2>
-> <script_name_3>          One line description of <script_name_3>
...
```

In order to get more information about a specific script run it with `-h` option or read `README.md` file in the appropriate subdirectory in script folder.

For example:


```
<script_name_1> -h
```

1.3.4 How to check current environment

```
uqt_info

# Python3 version:
...
# Customization (UQT_CUSTOM):
....
# Wanted Extensions (UQT_ADDINS):
    addin_name_1
    addin_name_2
    addin_name_3
    ...
# Loaded Extensions:
...
# DUT 'Default':
    unknown port ('UQT_PORT' not defined.)
```

1.4 Manual: About communicating with a DUT

The DUT communication is done through the use of OS 'ports': COMxx, /dev/ttyUSBxx, /dev/serial/xx. The related transport protocol is UART.

1.4.1 Communication Ports

To find the appropriate port for your DUT, please:

Windows (PowerShell):

- Open the Device Manager.
- Expand Ports (COM & LPT).
- Look for your DUT port (e.g. USB Serial Port (COM5)).
- Use the port number (e.g. COM5) to set the UQT_PORT variable.
- Set a default port:

```
$env:UQT_PORT="<port>"
```

- Verify the proper settings:

```
uqt_info
```

Linux:

- List the available ports using `ls /dev/serial/by-id/`.
- Look for the appropriate port (e.g. /dev/serial/by-id/usb-Nordic_Semiconductor_nRF52_USB_Product_<XYZ>-if00).
- Use the port name (e.g. /dev/serial/by-id/usb-Nordic_Semiconductor_nRF52_USB_Product_<XYZ>-if00) to set the UQT_PORT variable.
- Set a default port:

```
export UQT_PORT="<port>"
```

- Verify the proper settings:

```
uqt_info
```

Note: For UQT scripts that require specifying a communication port, the `--port` option is available. If this option is not explicitly provided, the scripts will by default use UQT_PORT environment variable as the communication port with the Device Under Test (DUT). The `--port` option can always be used to manually specify the port regardless of the UQT_PORT setting.

1.5 Manual: about configuring your DUT

1.5.1 How to get/set Device Configuration

```
# Get the list of available parameters:
get_config -l
# Get the value of all available parameters:
get_config all
# Set the default channel number to 5:
set_config ChannelNumber 5
```

1.5.2 How to get/set Calibration Parameters

```
# Get the list of available parameters:
get_cal -l
# Get the value of all cal parameters as binary stream:
get_cal -b all
# Backup all your calibration values to a file:
get_cal -fa all | tee my_calibration.txt
# Recover your calibration values from a file:
set_cal -i my_calibration.txt
```

In order to get more information about a specific script and/or use case please read the subsequent chapter or README.md file in the appropriate subdirectory.

2 scripts

2.1 Scripts Introduction

The **scripts** directory serves as the core functional hub of UQT library, housing a collection of essential scripts designed to provide a wide array of functionalities. Whether you are looking to manage devices, run UWB use cases, or handle specific scenarios, you'll find the tools you need here.

Each subdirectory within this folder is dedicated to a specific area of functionality, ensuring that the scripts are well-organized and easy to navigate. Within this directory, you'll encounter scripts that communicate with devices via UCI, alongside standalone "offline" tools and UQT supporting scripts.

For detailed information on how to use these scripts, please refer to the subsequent chapters or the README.md files located within the appropriate subdirectories. These resources will guide you through the specific use cases and help you make the most out of the available tools.

2.2 device

2.2.1 Device Scripts Introduction

The **device** directory introduces general functionality which is not related with any specific feature, but with a device itself. It means that in order to invoke these scripts you need a connected device. These scripts will communicate with a device using UCI interface.

Example scripts from this chapter are getting some information from a device, like statistics, firmware version or operations with calibration (get/set).

To learn more about detailed use cases, please read the subsequent chapters or README.md files in the appropriate subdirectories.

2.2.2 get_cal

This script retrieves from the device current calibration values.

2.2.2.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------|---|
| -p / --port | Specify communication interface |
| -l / --list | list available param names and their spec |
| -v / --verbose | prints additional debug information |
| -f / --format | Choose param display format. Available: r(repr), x(hex), b(bytes), or a(android param file). Default: natural |

2.2.2.2 Example

```
get_cal -p <port> ant_set0.tx_power_control
```

2.2.3 get_cap

This script retrieves DUT's (Device Under Test) capabilities through FiRa UCI commands CORE_GET_CAPS_INFO_CMD/CORE_GET_CAPS_INFO_RSP.

2.2.3.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------|-------------------------------------|
| -p / --port | Specify communication interface |
| -v / --verbose | prints additional debug information |

2.2.3.2 Example

```
get_cap -p <port>

# Get Device Capability Parameter

# Get Caps Info:
    status:                Ok (0x0)
    Caps:
[...]
```

2.2.4 get_config

This script retrieves the device configuration; it can be used to display firmware debug traces configuration.

2.2.4.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|-----------------|--|
| -p / --port | Specify communication interface |
| -l / --list | list available param names and their spec |
| -v / --verbose | prints additional debug information |
| -b / --as-bytes | show the key value as a byte stream |
| -x / --as-hex | show the key value in hex format |
| -r / --as-repr | show the key value in format used to set it back |

2.2.4.2 Example

```
get_config -p <port>
State                = DeviceState.Ready
[...]
```

2.2.5 get_device_info

This script displays information about the device based on information retrieved from the CORE_GET_DEVICE_INFO_RSP.

2.2.5.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|---------------|-------------------------------------|
| -p / -port | Specify communication interface |
| -v / -verbose | prints additional debug information |

2.2.5.2 Response Fields

Below are the details of each field in the response:

| Field | Length | Description |
|--------------------------|----------|--|
| Status | 1 Octet | Indicates the status of the response. |
| UCI Version | 2 Octets | Supported UCI version. |
| MAC Version | 2 Octets | Supported MAC version. |
| PHY Version | 2 Octets | Supported PHY version. |
| UCI Extension Version | 2 Octets | Supported UCI Extension version. |
| Vendor Specific Info Len | 1 Octet | The length of the vendor-specific information. |
| Vendor Specific Info | n Octets | Vendor-specific information such as chip version and chip variant. |

Note: For more details refer to CORE_GET_DEVICE_INFO_RSP in FIRA UCI Technical Specification.

2.2.5.2.1 Vendor Specific Info Fields

These fields contain vendor-specific information such as chip version and chip variant.

| Field | Description |
|--------------|---|
| QMF Version | Qorvo Mobile Firmware (QMF) version. |
| OEM Version | Original equipment manufacturer (OEM) version, possible to set by customer. |
| Build Job | Information about the build job. |
| SOC ID | System on Chip (SOC) identifier. |
| Device ID | Device identifier. |
| Packaging ID | Packaging type: 'sip' (System in Package) or 'soc' (System on Chip). |

Note: The fields packaging id and build job are optional and may not be present for each firmware or device.

2.2.5.3 Example

```
get_device_info -p <port>
```

Pinging device at COM18:

Get Device Info:

status: Ok (0x0)

[...]

2.2.6 reset_calibration

This script resets the DUT's calibration parameters to their default values.

2.2.6.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|---------------|---|
| -p / -port | Specify communication interface |
| -v / -verbose | prints additional debug information |
| -timeout | time in second until the script timeout |

2.2.6.2 Example

```
reset_calibration -p <port> --timeout 6
```

2.2.7 reset_device

This script resets the DUT by sending FiRa UCI Command CORE_DEVICE_RESET_CMD.

2.2.7.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|---------------|-------------------------------------|
| -p / -port | Specify communication interface |
| -v / -verbose | prints additional debug information |

2.2.7.2 Example

```
reset_device -p <port>
```

2.2.8 set_cal

This script pushes a specific calibration value by adding the selected key and its value.

2.2.8.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|---------------|---|
| -p / -port | Specify communication interface |
| -l / -list | list available param names and their spec |
| -v / -verbose | prints additional debug information |
| -f / -format | Choose param display format. Available: r(repr), x(hex), b(bytes), or a(android param file). Default: natural |

2.2.8.2 Example

```
set_cal -p <port> ant_set0.tx_power_control 3

INFO:      setting ant_set0.tx_power_control
          ant_set0.tx_power_control = Int8(3)
                                   = 3

Ok (0)
```

2.2.9 set_config

This script sets a configuration parameter value; it can be used to activate firmware debug traces.

2.2.9.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|---------------|---|
| -p / -port | Specify communication interface |
| -l / -list | list available param names and their spec |
| -v / -verbose | prints additional debug information |

2.2.9.2 Example

```
set_config ChannelNumber 5 -p <port>
OK (0)
```

2.2.10 load_cal

2.2.10.1 calib_files

2.2.10.1.1 Calibration Files Introduction

JSON calibration files are stored in the directory `scripts/device/load_cal/calib_files`. These files enable the configuration of default calibration settings for various targets.

The calibration and configuration data are encapsulated within JSON files, which can be passed as arguments to the `load_cal` script. This script processes the JSON file and transmits the settings to the device via UCI for device configuration.

2.2.10.1.1.1 Directory Structure

```
calib_files
├── <target_1>                                <- Default calibrations for <target_1>
│   ├── <antenna_1>.json                      <- JSON calibration file for <target_1> and <antenna_1>
│   └── <target_2>                            <- Default calibrations for <target_2>
│       ├── <antenna_1>.json                  <- JSON calibration file for <target_2> and <antenna_1>
│       ├── <antenna_2>.json                  <- JSON calibration file for <target_2> and <antenna_2>
│       └── ...
```

2.2.10.1.1.2 Customizing JSON Calibration Files

Default configuration JSON files serve as examples and can be customized to meet specific requirements. Calibration and configuration are managed through a Key/Value mechanism, reflected in the structure of these JSON files.

Note: Detailed descriptions of available Calibration and Configuration keys are provided in a separate document.

Example JSON file:

```
{
  "LUT": {
    "PDOA_LUT_0_CH5" : [
      [-2.9021, -1.5708],
      [3.0487, 1.4661],
      [3.1142, 1.5708]
    ],
    "PDOA_LUT_1_CH9" : [
      [-3.3905, -1.5708],
      [2.8451, 1.4661],
      [2.8932, 1.5708]
    ]
  },
  "calibrations": {
    "pdoa_lut0.data": "PDOA_LUT_0_CH5",
    "pdoa_lut1.data": "PDOA_LUT_1_CH9",
    "ant0.transceiver": "0x00",
    "ant0.port": "0x01",
    "ant0.lna": "0",
  }
}
```

2.2.10.1.2 DWM3001CDK

This directory contains a default calibration and configuration JSON file for the DWM3001CDK kit. The development board integrates a UWB transceiver module based on the Qorvo DW3110 IC with an attached planar Dual-Hoe (WB007) antenna and nRF52833 MCU.

As the development kit does not support the AoA capabilities, only one default calibration file is available:

- **dual-hoe_non_aoa.json**: This file contains default calibration and configuration settings for the DWM3001CDK setup not supporting AoA.

2.2.10.1.3 QM33120WDK1

This directory contains default calibration and configuration JSON files for the QM33120WDK1 kit.

Depending on the daughter board and antenna sets used, there are two files available:

- **jolie_aoa.json**: This file contains default calibration and configuration settings for the QM33120WDK1 setup supporting AoA.

Note: Compatible with the Nordic nRF52840 DK and a daughter board equipped with the QM33120W UWB transceiver featuring directional dual Jolie-AoA (JL359) antenna.

- **jolie_omni_non_aoa.json**: This file contains default calibration and configuration settings for the QM33120WDK1 setup not supporting AoA.

Note: Compatible with the Nordic nRF52840 DK and a daughter board equipped with the QM33110W UWB transceiver featuring omnidirectional single Jolie-Omni (JL159) antenna.

2.2.10.1.4 Type2AB EVB

This directory contains the default calibration and configuration JSON file for the Murata Type2AB EVB kit (Rev4.0). The evaluation board integrates a Murata Type2AB module based on the nRF52840 MCU and Qorvo QM33120W transceiver and utilizes two patch antennas.

As the development kit supports AoA capabilities, only one default calibration file is available:

- **patch_aoa.json**: This file contains the default calibration and configuration settings for the Type2AB setup supporting AoA.

Warning: The provided JSON configuration file is compatible only with the latest Type2AB EVB revision - Rev4.0 (PCB version: JS-1055). **Revision 3.0 (PCB version: JS-0989) is not supported.**

2.3 fir

2.3.1 FiRa Introduction

The **fira** directory introduces device ranging capabilities according to FiRa standard.

In order to know detailed description of each tool please read appropriate subchapters below or README.md files in appropriate subfolders.

2.3.2 run_fira_test_per_rx

Script **run_fira_test_per_rx** is provided to demonstrate the FiRa PER RX Test. In the Packet/bit Error Rate RX Test mode, the UWBS continues to look for UWB packets in a timely fashion (T_GAP) until a configured number of packets (NUM_PACKETS) have elapsed. The timing of the packet starts only after the successful reception of the first packet, otherwise UWBS looks for the first packet indefinitely. This test mode can be used to measure the receiver sensitivity of the UWB device.

2.3.2.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------------|---|
| -t / -time | Set the duration of the ranging session (in second); -1 - range forever |
| -p / -port | Set communication port |
| -c / -channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -i / -input-file | Recover test configuration from a test profile file |
| -v / -verbose | Print additional debug information |
| -randomized-psdu | Refer to RANDOMIZE_PSDU in FIRA UCI Extension for Testing (default 0) |
| -preamble-code-index | Refer to PREAMBLE_CODE_INDEX in FIRA UCI Technical Specification |
| -sfd-id | Refer to SFD_ID in FIRA UCI Technical Specification |
| -rframe-config | Refer to RFRAME_CONFIG in FIRA UCI Technical Specification (default 0) |
| -psdu-data-rate | Refer to PSDU_DATA_RATE in FIRA UCI Technical Specification |
| -phr-data-rate | Refer to BPRF_PHR_DATA_RATE in FIRA UCI Technical Specification |
| -preamble-duration | Refer to PREAMBLE_DURATION in FIRA UCI Technical Specification |
| -sts-length | Refer to STS_LENGTH in FIRA UCI Technical Specification |
| -nb-sts-segments | Refer to NUMBER_OF_STS_SEGMENTS in FIRA UCI Technical Specification |
| -psdu | ',' or '.' separated list of bytes |
| -num-packets | Refer to NUM_PACKETS in FIRA UCI Extension for Testing (default = 1000) |
| -t-gap | Refer to T_GAP in FIRA UCI Extension for Testing (default = 2000) |
| -timeout | Set timeout to receive the first package (in seconds). (default: 3) |
| -en-diag | Set the Qorvo ENABLE_DIAGNOSTIC parameter to 1 |
| -antenna-set-id | Set the antenna set to use for the session. (default: 0) |

2.3.2.2 Application

Refer to “Application Configuration Parameters” in FIRA UCI Technical Specification for the possible values on APP configuration parameters.

| Parameter Name | Len (octet) | ID | Description | De-fault |
|----------------|-------------|------|---|----------|
| NUM_PACKETS | 4 | 0x00 | No. of packets | 1000 |
| T_GAP | 4 | 0x01 | Gap between start of one packet to the next in us $T_GAP \gg \text{packet length}$ | 2000 |
| T_START | 4 | 0x02 | Max. time from the start of T_GAP to SFD found state in us | 450 |
| T_WIN | 4 | 0x03 | Max. time for which RX is looking for a packet from the start of T_GAP in us $T_WIN > T_START$ | 750 |
| RANDOMIZE_PSDU | 1 | 0x04 | 0 - No randomization 1 - Take first byte of data supplied by command and it shall be used as a seed for randomizing PSDU | 0 |

The PER RX Test shall be triggered by using TEST_PER_RX_CMD command.

The TEST_PER_RX_CMD command shall be issued only after applying all required Configuration parameters and the “Device Test Mode” session SHALL be in SESSION_STATE_IDLE Session State, otherwise UWBS will respond TEST_PER_RX_RSP with Status of STATUS_ERROR_SESSION_NOT_CONFIGURED indicating that session is not configured.

The UWBS shall respond TEST_PER_RX_RSP with the status of STATUS_OK and start PER Test. The number of packets to be received over UWB is configured by the NUM_PACKETS APP Configuration Parameter. UWBS shall notify TEST_PER_RX_NTF notification after completing the PER Rx test.

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|--|
| PSDU Data | N Octets | PSDU Data[0:N] bytes. $0 \leq N \leq 127$ for BPRF, $0 \leq N \leq 4095$ for HPRF. |

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|-------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC]. |

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|---|
| Status | 1 | Notify host after receiving NUM_PACKETS. Refer generic status codes |
| ATTEMPTS | 4 | No. of RX attempts |
| ACQ_DETECT | 4 | No. of times signal was detected |
| ACQ_REJECT | 4 | No. of times signal was rejected |
| RX_FAIL | 4 | No. of times RX did not go beyond ACQ stage |
| SYNC_CIR_READY | 4 | No. of times sync CIR ready event was received |
| SFD_FAIL | 4 | No. of time RX was stuck at either ACQ detect or sync CIR ready |
| SFD_FOUND | 4 | No. of times SFD was found |
| PHR_DEC_ERROR | 4 | No. of times PHR decode failed |
| PHR_BIT_ERROR | 4 | No. of times PHR bits in error |
| PSDU_DEC_ERROR | 4 | No. of times payload decode failed |
| PSDU_BIT_ERROR | 4 | No. of times payload bits in error |
| STS_FOUND | 4 | No. of times STS detection was successful |
| EOF | 4 | No. of times end of frame event was triggered |

2.3.3 run_fira_test_periodic_tx

Script **run_fira_test_periodic_tx** is provided to demonstrate FiRa Periodic TX Test. In the Periodic TX Test mode, the UWBS continues to send UWB packets until a configured number of packets (NUM_PACKETS) have been sent. This test mode may be used to measure characteristics like signal power, bandwidth and IEEE spectral mask of the transmitted signal.

2.3.3.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------------|--|
| -t / -time | Set the duration of the ranging session (in seconds); -1 - range forever |
| -p / -port | Specify communication interface |
| -c / -channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -i / -input-file | Recover test configuration from a test profile file |
| -v / -verbose | Prints additional debug information |
| -randomized-psdu | Refer to RANDOMIZE_PSDU in FIRA UCI Extension for Testing (default 0) |
| -preamble-code-index | Refer to PREAMBLE_CODE_INDEX in FIRA UCI Technical Specification |
| -sfd-id | Refer to SFD_ID in FIRA UCI Technical Specification |
| -rframe-config | Refer to RFRAME_CONFIG in FIRA UCI Technical Specification (default 0) |
| -psdu-data-rate | Refer to PSDU_DATA_RATE in FIRA UCI Technical Specification |
| -phr-data-rate | Refer to BPRF_PHR_DATA_RATE in FIRA UCI Technical Specification |
| -preamble-duration | Refer to PREAMBLE_DURATION in FIRA UCI Technical Specification |
| -nb-sts-segments | Refer to NUMBER_OF_STS_SEGMENTS in FIRA UCI Technical Specification |
| -sts-length | Refer to STS_LENGTH in FIRA UCI Technical Specification |
| -psdu | '.' or ',' separated list of bytes |
| -num-packets | Refer to NUM_PACKETS in FIRA UCI Extension for Testing (default = 1000) |
| -t-gap | Refer to T_GAP in FIRA UCI Extension for Testing (default = 2000) |
| -timeout | Set timeout to receive the first package (in seconds). (default: 3) |
| -en-diag | Set the Qorvo ENABLE_DIAGNOSTIC parameter to 1 |
| -antenna-set-id | Set the antenna set to use for the session. (default: 0) |

2.3.3.2 Application

Refer to "Application Configuration Parameters" in FIRA UCI Technical Specification for the possible values on APP configuration parameter.

| Parameter Name | Len (octet) | ID | Description | De-fault |
|----------------|-------------|------|---|----------|
| NUM_PACKETS | 4 | 0x00 | No. of packets | 1000 |
| T_GAP | 4 | 0x01 | Gap between start of one packet to the next in us. | 2000 |
| RANDOMIZE_PSDU | 1 | 0x04 | 0 - No randomization 1 - Take first byte of data supplied by command and it shall be used as a seed for randomizing PSDU | 0 |

The periodic TX Test shall be triggered by using TEST_PERIODIC_TX_CMD command.

The TEST_PERIODIC_TX_CMD command SHALL be issued only after applying all required configuration parameters and the "Device Test Mode" session shall be in SESSION_STATE_IDLE Session State, otherwise UWBS SHALL respond TEST_PERIODIC_TX_RSP with Status of STATUS_ERROR_SESSION_NOT_CONFIGURED indicating that Test Session is not configured.

The UWBS shall respond TEST_PERIODIC_TX_RSP with the status of STATUS_OK and starts Periodic Test. The UWBS SHALL periodically starts sending UWB packets with PSDU Data as a payload. The periodicity is configured by the T_GAP Test Configuration Parameter and the number of packets to be transferred is configured by NUM_PACKETS APP Configuration Parameter.

The UWBS shall notify TEST_PERIODIC_TX_NTF notification with the status of STATUS_OK after NUM_PACKETS packets are sent over UWB to the intended destination UWB device.

TEST_PERIODIC_TX_CMD

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|--|
| PSDU Data | N Octets | PSDU Data[0:N] bytes; $0 \leq N \leq 127$ for BPRF; $0 \leq N \leq 4095$ for HPRF. |

TEST_PERIODIC_TX_RSP

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|-------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC]. |

TEST_PERIODIC_TX_NTF

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|-------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC]. |

2.3.4 run_fira_test_rx

Script **run_fira_test_rx** is provided to demonstrate FiRa RX Test. This RF test can be used to report signal parameters like SNR, AOA etc. Generally, this test is used to receive a single packet by using the TEST_RX_CMD command.

2.3.4.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------------|--|
| -p / -port | Specify communication interface |
| -c / -channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -v / -verbose | Print additional debug information |
| -preamble-code-index | Refer to PREAMBLE_CODE_INDEX in FIRA UCI Technical Specification |
| -sfd-id | Refer to SFD_ID in FIRA UCI Technical Specification |
| -rframe-config | Refer to RFRAME_CONFIG in FIRA UCI Technical Specification (default 0) |
| -psdu-data-rate | Refer to PSDU_DATA_RATE in FIRA UCI Technical Specification |
| -phr-data-rate | Refer to BPRF_PHR_DATA_RATE in FIRA UCI Technical Specification |
| -preamble-duration | Refer to PREAMBLE_DURATION in FIRA UCI Technical Specification |
| -nb-sts-segments | Refer to NUMBER_OF_STS_SEGMENTS in FIRA UCI Technical Specification |
| -sts-length | Refer to STS_LENGTH in FIRA UCI Technical Specification |
| -en-diag | Set the Qorvo ENABLE_DIAGNOSTIC parameter to 1 |
| -antenna-set-id | Set the antenna set to use for the session. (default: 0) |

2.3.4.2 Application

Refer to “Application Configuration Parameters” in FIRA UCI Technical Specification for the possible values on APP configuration parameters.

Test configuration parameters for RX Test

| Parameter Name | Len (octets) | ID | Description |
|----------------|--------------|------|--|
| RMARKER_TX_ST | 4 | 0x06 | Start time of TX in $1/(128 \times 499.2\text{MHz})$ units |
| STS_INDEX_AUTC | 1 | 0x08 | 0x00: STS_INDEX config value is used for all PER Rx/ Periodic TX test. (default) Commented [SV4]: CR-241 |

The RX Test shall be triggered by using the TEST_RX_CMD command and UWBS shall respond by TEST_RX_RSP when a command is accepted successfully. The Configuration Parameters defined in the tables below affect the behavior of the test.

The TEST_RX_CMD command shall be issued only after applying all required configuration parameters and the “Device Test Mode” session SHALL be in SESSION_STATE_IDLE Session State, otherwise UWBS SHALL respond TEST_RX_RSP with Status of STATUS_ERROR_SESSION_NOT_CONFIGURED, indicating that session is not configured.

UWBS shall notify TEST_RX_NTF notification after the UWB packet is received from the intended device.

TEST_RX_CMD

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|---------------|
| Command | 0 Octets | Start RX Test |

TEST_RX_RSP

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|-------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC]. |

TEST_RX_NTF

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|---|
| Status | 1 | Refer to generic status codes |
| RX_DONE_TS_IN | 4 | Integer part of timestamp $1/124.8\text{MHz}$ ticks |
| RX_DONE_TS_F | 2 | Fractional part of timestamp in $1/(128 \times 499.2\text{MHz})$ ticks |
| AoA Azimuth | 2 | AoA Azimuth in degrees and it is a signed value in Q9.7 format. This field is zero if AOA_RESULT_REQ = 0. |
| AoA Elevation | 2 | AoA Elevation in degrees and it is a signed value in Q9.7 format. This field is zero if AOA_RESULT_REQ = 0. |
| ToA Gap | 1 | ToA of main path minus ToA of first path in nanoseconds |
| PHR | 2 | Received PHR (bits 0-12 as per IEEE spec) |
| PSDU Data Length | 2 | Length of PSDU Data(N) to follow |
| PSDU Data | N Octets | PSDU Data[0:N] bytes; $0 \leq N \leq 127$ for BPRF; $0 \leq N \leq 4095$ for HPRF. |

2.3.4.3 Example

Use 2 different shells, one for each DUT. They will be called here after DUT-TX and DUT-RX.

In shell 'DUT-RX', start the device in a 'listener' test mod:

```
run_fira_test_rx -p <dut rx port>
```

In shell 'DUT-TX', request a given payload to be sent:

```
run_fira_test_tx -p <dut tx port> --psdu '0a.0b.0c.0d.0e.0f'
```

In shell 'DUT-RX', verify the received data: You should expect the same data to be received ...

```
RxTestOutput gid:13, oid:5, Test Result:
...
PSDU data:      0a.0b.0c.0d.0e.0f
...
```

2.3.5 run_fira_test_ss_twr

Script **run_fira_test_ss_twr** is provided to demonstrate FiRa SS-TWR Test Mode. This mode can be used to measure single SS-TWR ToF using SP3 packets.

- Initiator transmits the POLL packet and waits for a RESPONSE packet from the responder, after SLOT_DURATION.
- Initiator then reports the time difference between the two packets as the round-trip time to AP.
- Similarly, responder waits for the POLL packet, transmits a RESPONSE packet after SLOT_DURATION and reports the time difference between the two packets as the reply time to AP. Based on these two measurements, AP can determine the ToF based on the SS-TWR formula.

2.3.5.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------------|---|
| -p / -port | Specify communication interface |
| -c / -channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -r / -responder | Start as responder (default initiator) mode |
| -v / -verbose | Print additional debug information |
| -preamble-code-index | Refer to PREAMBLE_CODE_INDEX in FIRA UCI Technical Specification |
| -sfd-id | Refer to SFD_ID in FIRA UCI Technical Specification |
| -phr-data-rate | Refer to BPRF_PHR_DATA_RATE in FIRA UCI Technical Specification |
| -preamble-duration | Refer to PREAMBLE_DURATION in FIRA UCI Technical Specification |
| -nb-sts-segments | Refer to NUMBER_OF_STS_SEGMENTS in FIRA UCI Technical Specification |
| -sts-length | Refer to STS_LENGTH in FIRA UCI Technical Specification |
| -en-diag | Set the Qorvo ENABLE_DIAGNOSTIC parameter to 1 |
| -antenna-set-id | Set the antenna set to use for the session. (default: 0) |

2.3.5.2 Application

Refer to “Application Configuration Parameters” in FIRA UCI Technical Specification for the possible values on APP configuration parameters.

Test configuration parameters for FiRa SS-TWR Test

| Parameter Name | Len (octets) | ID | Description |
|-------------------|--------------|------|--|
| STS_INDEX_AUTO_IN | 1 | 0x08 | 0x00: STS_INDEX config value is used for all PER Rx/ Periodic TX test. (default) |

AP shall use the TEST_SS_TWR_CMD command to trigger the SS-TWR ranging test for SP3 packets and UWBS shall respond by TEST_SS_TWR_RSP when a command is accepted successfully.

The TEST_SS_TWR_CMD command shall be issued only after applying all the required configuration parameters and the “Device Test Mode” session SHALL be in SESSION_STATE_IDLE state, otherwise UWBS SHALL respond TEST_SS_TWR_RSP with Status of STATUS_ERROR_SESSION_NOT_CONFIGURED, indicating that session is not configured. UWBS SHALL notify TEST_SS_TWR_NTF notification after completing a single SS-TWR ranging measurement round involving POLL and RESPONSE packets.

TEST_SS_TWR_CMD

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|--|
| PSDU Data | N Octets | PSDU Data[0:N] bytes; 0 <= N <= 127 for BPRF; 0 <= N <= 4095 for HPRF. |

TEST_SS_TWR_RSP

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|-------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC]. |

TEST_SS_TWR_NTF

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|--|
| Status | 1 | Refer to generic status codes |
| Measurement | 4 | Contains Tround time of Initiator or Treply time of Responder depending on DEVICE_ROLE option. This is expressed in $1/(128 * 499.2\text{Mhz})$ ticks. |

2.3.6 run_fira_twr

Script **run_fira_twr** is provided to demonstrate a FiRa session ranging which can be easily modified.

2.3.6.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------------|---|
| -t / -time | Set the duration of the ranging session (in second); -1 - range forever |
| -p / -port | Specify communication interface |
| -c / -channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -s / -session | Set session ID (default: 42) |
| -v / -verbose | Prints additional debug information |
| -controlee | Refer to DEVICE_TYPE in FIRA UCI Technical Specification |
| -round | Refer to RANGING_ROUND_USAGE in FIRA UCI Technical Specification |
| -round-ctrl | Refer to RANGING_ROUND_CONTROL in FIRA UCI Technical Specification |
| -en-key-rot | Refer to KEY_ROTATION in FIRA UCI Technical Specification |
| -key-rot-rate | Refer to KEY_ROTATION_RATE in FIRA UCI Technical Specification |
| -sts | Refer to STS_CONFIG in FIRA UCI Technical Specification |
| -slot-span | Refer to SLOT_DURATION in FIRA UCI Technical Specification |
| -node | Refer to MULTI_NODE_MODE in FIRA UCI Technical Specification |
| -ranging-span | Refer to RANGING_DURATION in FIRA UCI Technical Specification |
| -en-diag | Set the Qorvo ENABLE_DIAGNOSTIC parameter to 1 |
| -diag-fields | Set the Qorvo DIAGNOSTIC_FRAME_REPORTS_FIELD value OR flags: metrics, aoa, cir, cfo. (default: metrics) |
| -meas-max | Refer to MAX_NUMBER_OF_MEASUREMENTS in FIRA UCI Technical Specification |
| -skey SKEY | Refer to SESSION_KEY in FIRA UCI Technical Specification |
| -mac | Refer to DEVICE_MAC_ADDRESS in FIRA UCI Technical Specification |
| -dest-mac | Refer to DST_MAC_ADDRESS in FIRA UCI Technical Specification |
| -frame | Refer to RFRAME_CONFIG in FIRA UCI Technical Specification |
| -ssession | Refer to SUB_SESSION_ID in FIRA UCI Technical Specification |
| -sskey | Refer to SUB_SESSION_KEY in FIRA UCI Technical Specification |
| -en-rssi | Refer to RSSI_REPORTING in FIRA UCI Technical Specification |
| -stats | Enable Statistics report at end of the run |
| -diag_dump | Dump the Diagnostics in the provided JSON file |
| -n_controlees | Refer to NUMBER_OF_CONTROLEES in FIRA UCI Technical Specification |
| -block_stride_length | Refer to BLOCK_STRIDE_LENGTH in FIRA UCI Technical Specification |
| -sts-length | Refer to STS_LENGTH in FIRA UCI Technical Specification |
| -vendor-id | Refer to VENDOR_ID in FIRA UCI Technical Specification |
| -static-sts | Refer to STATIC_STS_IV FIRA UCI Technical Specification |
| -aoa-report | Refer to AOA_RESULT_REQ FIRA UCI Technical Specification |
| -preamble-idx | Refer to PREAMBLE_CODE_INDEX FIRA UCI Technical Specification |
| -sfd | Refer to SFD_ID FIRA UCI Technical Specification |
| -slots-per-rr | Refer to SLOTS_PER_RR FIRA UCI Technical Specification |
| -hopping-mode | Refer to HOPPING_MODE FIRA UCI Technical Specification |

Warning(!), --diag_dump has an effect only with the --stats option.

The Diagnostics parameter save the diagnostics report in a json file named range_data_<year>-<month>-<day>-<time>.json. For instance: range_data_23-04-12-10h47m25s.json

The report contains one entry per Fira ranging sequence, each of these entries contains one entry per frame exchanged.

2.3.6.2 Example with Default values

Initialize a TWR FiRa session as controller on the first board.

```
run_fira_twr -p <controller port>
```

Open a second command shell in the Python script location.

Initialize a TWR FiRa session as a controlee on the second board.

```
run_fira_twr -p <controlee port> --controlee
```

Output of the script running on the controlee side with default parameter:

```
Initializing session 42...
Session 2 -> Init (StateChangeWithSessionManagementCommands)
Using Fira 2.0 session handle is : 2
Setting session 2 config ...
  DeviceType (0x0):           0x0
  DeviceRole (0x11):          0x0
  MultiNodeMode (0x3):         0x0
  RangingRoundUsage (0x1):      0x2
  DeviceMacAddress (0x6):       0x1
  ChannelNumber (0x4):          0x9
  ScheduleMode (0x22):          0x1
  StsConfig (0x2):              0x0
  RframeConfig (0x12):          0x3
  ResultReportConfig (0x2e):    0xb
  VendorId (0x27):              0x708
  StaticStsIv (0x28):           0x60504030201
  AoaResultReq (0xd):           0x1
  UwbInitiationTime (0x2b):      0x0
  PreambleCodeIndex (0x14):     0xa
  SfdId (0x15):                 0x2
  SlotDuration (0x8):            0x960
  RangingInterval (0x9):         0xc8
  SlotsPerRr (0x1b):             0x19
  MaxNumberOfMeasurements (0x32): 0x0
  HoppingMode (0x2c):            0x0
  RssiReporting (0x13):          0x0
  BlockStrideLength (0x2d):      0x0
  NumberOfControlees (0x5):      0x1
  DstMacAddress (0x7):           [0]
  StsLength (0x35):              0x1
Session 6 -> Idle (StateChangeWithSessionManagementCommands)
Starting ranging...
Device -> Active
Session 6 -> Active (StateChangeWithSessionManagementCommands)

[...]

# Ranging Data:
  session handle:      2
  sequence n:          8
  ranging interval:    200 ms
  measurement type:    Twr
  Mac add size:        2
```

(continues on next page)

(continued from previous page)

```

primary session id: 0x0
n of measurement: 1
# Measurement 1:
  status:           Ok (0x0)
  mac address:      00:00 hex
  is nlos meas:     Unknown
  distance:         62.0 cm
  AoA azimuth:      -10.6328125 deg
  AoA az. FOM:       92.0 %
  AoA elevation:     0.0 deg
  AoA elev. FOM:     0.0
  AoA dest azimuth: 0.0 deg
  AoA dest az. FOM:  0.0 %
  AoA dest elevation: 0.0 deg
  AoA dest elev. FOM: 0.0 %
  slot in error:    0
  rssi:             -0.0 dBm

```

[...]

Stopping ranging...

Session 2 -> Idle (StateChangeWithSessionManagementCommands)

Device -> Ready

Deinitializing session...

Session 2 -> DeInit (StateChangeWithSessionManagementCommands)

Ok

2.3.6.3 Example with Statistics, Diagnostic and RSSI

Initialize a TWR FiRa session as controller on the first board.

```
run_fira_twr -p <controller port> --stats --en-diag -en-rssi
```

Open a second command shell in the Python script location.

Initialize a TWR FiRa session as contolee on the second board (in this example, in COM40).

```
run_fira_twr -p <controlee port> --controlee
```

Output of the script running on the controller side:

```

Initializing session 42...
Session 4 -> Init (StateChangeWithSessionManagementCommands)
Using Fira 2.0 session handle is : 4
Setting session 4 config ...
  DeviceType (0x0):           0x0
  DeviceRole (0x11):          0x0
  MultiNodeMode (0x3):        0x0
  RangingRoundUsage (0x1):     0x2
  DeviceMacAddress (0x6):      0x1
  ChannelNumber (0x4):         0x9
  ScheduleMode (0x22):         0x1
  StsConfig (0x2):             0x0
  RframeConfig (0x12):         0x3
  ResultReportConfig (0x2e):    0xb

```

(continues on next page)

(continued from previous page)

```

VendorId (0x27):          0x708
StaticStsIv (0x28):       0x60504030201
AoarResultReq (0xd):       0x1
UwbInitiationTime (0x2b):  0x0
PreambleCodeIndex (0x14):  0xa
SfdId (0x15):             0x2
SlotDuration (0x8):        0x960
RangingInterval (0x9):     0xc8
SlotsPerRr (0x1b):         0x19
MaxNumberOfMeasurements (0x32): 0x0
HoppingMode (0x2c):         0x0
RssiReporting (0x13):       0x0
BlockStrideLength (0x2d):   0x0
NumberOfControlees (0x5):   0x1
DstMacAddress (0x7):        [0]
StsLength (0x35):          0x1

```

Session 4 -> Idle (StateChangeWithSessionManagementCommands)

Starting ranging...

Device -> Active

Session 4 -> Active (StateChangeWithSessionManagementCommands)

[...]

Ranging Data:

```

session handle:          2
sequence n:              23
ranging interval:        200 ms
measurement type:        Twr
Mac add size:            2
primary session id:      0x0
n of measurement:        1
# Measurement 1:
  status:                 Ok (0x0)
  mac address:            00:01 hex
  is nlos meas:           Unknown
  distance:               76.0 cm
  AoA azimuth:            0.0 deg
  AoA az. FOM:            0.0 %
  AoA elevation:          0.0 deg
  AoA elev. FOM:          0.0
  AoA dest azimuth:       7.296875 deg
  AoA dest az. FOM:       92.0 %
  AoA dest elevation:     0.0 deg
  AoA dest elev. FOM:     0.0 %
  slot in error:          0
  rssi:                   -60.0 dBm

```

Ranging Diagnostic Data:

```

Session handle:          2
Sequence n:              23
Nbr of reports:          6
# Ranging Diag. Report 0:
  Message id:             Control
  Action:                 Tx
  Antenna_set:            0

```

(continues on next page)

(continued from previous page)

```

Nbr of fields: 1
# Frame Status Report:
    is processing ok : 1
    is wifi activated : 0
# Ranging Diag. Report 1:
    Message id:    RangingInitiation
    Action:        Tx
    Antenna_set:   0
    Nbr of fields: 1
    # Frame Status Report:
        is processing ok : 1
        is wifi activated : 0
# Ranging Diag. Report 2:
    Message id:    RangingResponse
    Action:        Rx
    Antenna_set:   0
    Nbr of fields: 3
    # Frame Status Report:
        is processing ok : 1
        is wifi activated : 0
# CFO Report:
    cfo:          -1.669 ppm
# Segment Metrics Reports:
    Nbr of Segment Metrics: 1
    # Segment Metrics    0:
        segment type:    1
        primary_rcv:     1
        receiver Id:     0x0
        noise_value:     -80
        rsl_dbm:          -64.18359375
        path1_rsl_dbm:    -65.88671875
        path1_idx:        362
        path1_snr:        14.11328125
        path1_t:          23183
        peak_rsl_dbm:     -64.18359375
        peak_idx:         704
        peak_snr:         15.81640625
        peak_t:           45056
# Ranging Diag. Report 3:
    Message id:    RangingFinal
    Action:        Tx
    Antenna_set:   0
    Nbr of fields: 1
    # Frame Status Report:
        is processing ok : 1
        is wifi activated : 0
# Ranging Diag. Report 4:
    Message id:    MeasurementReport
    Action:        Tx
    Antenna_set:   0
    Nbr of fields: 1
    # Frame Status Report:
        is processing ok : 1
        is wifi activated : 0
# Ranging Diag. Report 5:

```

(continues on next page)

(continued from previous page)

```

Message id:    RangingResultReport
Action:        Rx
Antenna_set:   0
Nbr of fields: 3
# Frame Status Report:
    is processing ok : 1
    is wifi activated : 0
# CFO Report:
    cfo:         -1.714 ppm
# Segment Metrics Reports:
    Nbr of Segment Metrics: 1
    # Segment Metrics 0:
        segment type:      0
        primary_recv:      1
        receiver Id:       0x0
        noise_value:       -80
        rsl_dBm:           -56.03515625
        path1_rsl_dbm:     -57.69140625
        path1_idx:         739
        path1_snr:         22.30859375
        path1_t:           47326
        peak_rsl_dbm:      -56.03515625
        peak_idx:          320
        peak_snr:          23.96484375
        peak_t:            20480

```

[...]

Deinitializing session...

Session 2 -> DeInit (StateChangeWithSessionManagementCommands)

Device -> Ready

Ok

Device: 00:01

```

    25 Successful/ 26 Total
    AVG Ranging: 68.80
    STDEV Ranging: 3.75
    AVG AoA Azimuth: 0.000
    STDEV AoA Azimuth: 0.000
    AVG AoA Elevation: 0.000
    STDEV AoA Elevation: 0.000

```

Statistics of the ranging are calculated at the end of the script.

2.3.6.4 Example for one-to-many Ranging

Initialize a One-To-Many TWR FiRa session as controller on the first board.

```
run_fira_twr -p <controller port> --node onetomany --dest-mac [0x01,0x02] --n_controlees 2
```

Open a second command shell in the Python script location.

Initialize a TWR FiRa session as controlee on the second board (in this example, in COM40).

```
run_fira_twr -p <controlee 1 port> --node onetomany --controlee --mac 1
```

Open a third command shell in the Python script location.

Initialize a TWR FiRa session as controlee on the third board (in this example, in COM18).

```
run_fira_twr -p <controlee 2 port> --node onetomany --controlee --mac 2
```

Output of the script running on the controller side:

```
Initializing session 42...
Session 42 Init (StateChangeWithSessionManagementCommands)
Setting session 42 config ...
DeviceRole (0x11):           0x1
DeviceType (0x0):           0x1
MultiNodeMode (0x3):        0x1
RangingRoundUsage (0x1):     0x2
DeviceMacAddress (0x6):      0x0
ChannelNumber (0x4):        0x9
ScheduleMode (0x22):        0x1
CapSizeRange (0x20):        0x510
StsConfig (0x2):            0x0
RframeConfig (0x12):        0x3
ResultReportConfig (0x2e):   0xf
VendorId (0x27):            0x708
StaticStsIv (0x28):         0x60504030201
AoaResultReq (0xd):         0x1
UwbInitiationTime (0x2b):    0x3e8
PreambleCodeIndex (0x14):    0x9
SfdId (0x15):              0x2
SlotDuration (0x8):         0x960
RangingInterval (0x9):      0xc8
SlotsPerRr (0x1b):         0x19
MaxNumberOfMeasurements (0x32): 0x0
HoppingMode (0x2c):         0x0
RssiReporting (0x13):       0x1
NumberOfControlees (0x5):    0x2
DstMacAddress (0x7):        [1, 2]
Starting ranging...
Session 42 Idle (StateChangeWithSessionManagementCommands)
Device Active
Session 42 Active (StateChangeWithSessionManagementCommands)

[...]

# Ranging Data:
  session id:      42
  sequence n:      0
  ranging interval: 200 ms
  measurement type: Twr
  Mac add size:    2
  primary session id: 0x0
  n of measurement: 2
# Measurement 1:
  status:          Ok (0x0)
  mac address:     01.00
  is nlos meas:    no
  distance:        45.0 cm
  AoA azimuth:     -30.9375 deg
  AoA az. FOM:     88.0 %
  AoA elevation:   0.0 deg
```

(continues on next page)

(continued from previous page)

```
AoA elev. FOM:      0.0
AoA dest azimuth:   10.375 deg
AoA dest az. FOM:   92.0 %
AoA dest elevation: 0.0 deg
AoA dest elev. FOM: 0.0 %
slot in error:      0
rssi:               -63.0 dB
# Measurement 2:
status:             Ok (0x0)
mac address:        02.00
is nlos meas:       no
distance:           22.0 cm
AoA azimuth:        -66.578125 deg
AoA az. FOM:        92.0 %
AoA elevation:      0.0 deg
AoA elev. FOM:      0.0
AoA dest azimuth:   0.0 deg
AoA dest az. FOM:   0.0 %
AoA dest elevation: 0.0 deg
AoA dest elev. FOM: 0.0 %
slot in error:      0
rssi:               -35.5 dB
```

```
[...]
```

```
Stopping ranging...
```

```
Deinitializing session...
```

```
Session 42 DeInit (StateChangeWithSessionManagementCommands)
```

```
Device Ready
```

```
Ok
```

2.4 qorvo

2.4.1 Qorvo Specific Scripts Introduction

The **qorvo** directory contains tests that evaluate various functionalities of Qorvo UWB chip. Each script in this folder is designed to perform a specific test, assessing various aspects of performance and functionality.

For detailed information on using these tests, please read the subsequent chapters or README.md files in the appropriate subdirectories.

2.4.2 run_qorvo_test_pll_lock

Script **run_qorvo_test_pll_lock** is provided to demonstrate Qorvo PLL Lock TX Test. This test requests the UWB radio to lock the PLL (IDLE_PLL) and reports the lock status. The test sets the radio to INIT_RC state once completed.

2.4.2.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|----------------|---|
| -p / --port | Specify communication interface |
| -c / --channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -v / --verbose | prints additional debug information |

2.4.2.2 Application

The Qorvo PLL Lock TX Test shall be triggered by using TEST_PLL_LOCK_CMD command and UWBS shall respond by TEST_PLL_LOCK_RSP when command is accepted successfully.

TEST_PLL_LOCK_CMD (GID = 0xB, OID = 0x1)

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|-------------|
| N/A | N/A | N/A |

TEST_PLL_LOCK_RSP (GID = 0xB, OID = 0x2)

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC] |

TEST_PLL_LOCK_NTF (GID = 0xB, OID = 0x2)

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|------------------------------|
| TLV count | 1 | The number of TLVs following |
| TLF list | 1 | See TLV descriptions below |

TLVs TEST_PLL_LOCK_NTF

| Type | Length | Value / Description |
|------|------------|---|
| 0x01 | 1 octet | Error code: 0 - SUCCESS: see PLL lock status table 1 - PLL_LOCK_ERROR: setting the channel failed 2 - INTERNAL_ERROR: setting the PLL state failed |
| 0x02 | 4 octet | PLL_STATUS_CH9_BIST_FAIL_BIT_MASK (0x4000): PLL channel 9 BIST fail PLL_STATUS_CH5_BIST_FAIL_BIT_MASK (0x2000): PLL channel 5 BIST fail PLL_STATUS_LD_CODE_BIT_MASK (0x1f00): Counter-based lock-detect status indicator PLL_STATUS_XTAL_AMP_SETTLED_BIT_MASK (0x0040): Status flag from the XTAL indicating that the amplitude has settled PLL_STATUS_VCO_TUNE_UPDATE_BIT_MASK (0x0020): Flag to indicate that the COARSE_TUNE codes have been updated by cal and are ready to read PLL_STATUS_PLL_OVRFLOW_BIT_MASK (0x0010): PLL calibration flag indicating all VCO_TUNE values have been cycled through PLL_STATUS_PLL_HI_FLAG_BIT_MASK (0x0080): VCO freq too high indicator (active-high) PLL_STATUS_PLL_LO_FLAG_N_BIT_MASK (0x0004): VCO freq too low indicator (active-low) PLL_STATUS_PLL_LOCK_FLAG_BIT_MASK (0x0002): PLL lock flag PLL_STATUS_CPC_CAL_DONE_BIT_MASK (0x0001): PLL cal done and PLL locked |

2.4.3 run_qorvo_test_tx_cw

Script **run_qorvo_test_tx_cw** is provided to demonstrate Qorvo Continuous Wave TX Test. This test configures the device to transmit a Continuous Wave (CW) at a specified channel of Qorvo UWB radio to transmit a Continuous Wave (CW) at a specified channel frequency. This may be of use as part of the crystal trimming procedure.

2.4.3.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Values |
|---------------|---|
| -p / -port | Specify communication interface |
| -c / -channel | Refer to CHANNEL_NUMBER in FIRA UCI Technical Specification |
| -t / -time | set the duration of the ranging session (in second); -1 - range forever |
| -v / -verbose | prints additional debug information |

2.4.3.2 Application

APP configuration parameters for Continuous Wave TX Test

| Parameter Name | Tag | Length | Description |
|----------------|------|--------|---|
| CHANNEL_NUMBER | 0x04 | 1 | 0x05 for channel 5; >0x09 for channel 9 |

Test configuration parameters for Continuous Wave TX Test

| Parameter Name | Tag | Length | Description |
|----------------------|------|--------|----------------------------|
| TX_ANTENNA_SELECTION | 0xE7 | 1 | ID of the TX antenna group |

The Qorvo Continuous Wave TX Test shall be triggered by using TEST_TX_CW_CMD command and UWBS SHALL respond by TEST_TX_CW_CMD when a command is accepted successfully.

TEST_TX_CW_CMD (GID = 0xB, OID = 0x1)

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|---------------------|
| Enable | 1 | 1 = start, 0 = stop |

TEST_TX_CW_RSP (GID = 0xB, OID = 0x1)

| Payload Field(s) | Size (octet) | Description |
|------------------|--------------|------------------------------------|
| Status | 1 | Status code as per [FIRA_UCI_SPEC] |

2.5 utils

2.5.1 Utilities Scripts Introduction

The **utils** directory contains general utilities that function as standalone tools or supporting scripts for the UQT package. These scripts are designed to work independently, without need of a connected device or communicating with any devices.

To learn more about detailed use cases, please read the subsequent chapters or README.md files in the appropriate subdirectories.

2.5.2 decode_uci

This script decodes command, response, and notification byte streams into a human-readable format. For more details, use `decode_uci -h`.

2.5.2.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Description |
|---------------|--|
| bytes | Byte stream |
| -o / --output | Set output file path. (default: ./tmp.csv) |

2.5.2.1.1 Byte Stream Format

The byte stream should be a series of bytes in the format: 1, 2, 3, etc. Each byte can be separated by:

- No separator
- A space ()
- A dot (.)
- A colon (:)

Note: If using a space () as the separator, the entire byte stream must be enclosed in single quotes (' ').

2.5.2.2 Example

Examples:

```
decode_uci 20.02.00.00
decode_uci '20 02 00 00'
decode_uci 410300020000 41.00.00.01.00 61.02.00.06.2a.00.00.00.00.00
decode_uci 410300020000 41.00.00.01.00 61.02.00.06.2a.00.00.00.00.00 -o ./output_file.csv
```

2.5.3 fp

Script **fp** is provided for handling conversion between natural and fixed-point numbers.

2.5.3.1 Parameters

Arguments with expected parameter available in this script:

| Parameter | Description |
|----------------|---|
| v | Value to convert. May be an int, float or bytearray |
| I | Number of bits for the integer part |
| F | Number of bits for the fractional part |
| -r / --reverse | Convert a fix point to float instead (default: False) |
| -s / --signed | Presence of a sign bit |

2.5.3.2 Example

```
fp 28 7 1
0x38
```

2.5.4 uqt_info

Print environment information

2.5.4.1 Example

```
uqt_info

# Python3 version:
...
# Customization (UQT_CUSTOM):
....
# Wanted Extensions (UQT_ADDINS):
    addin_name_1
    addin_name_2
    addin_name_3
    ...
# Loaded Extensions:
...
# DUT 'Default':
    unknown port ('UQT_PORT' not defined.)
```

2.5.5 uqt_ls

List available tools

2.5.5.1 Example

```
uqt_ls
-> <script_name_1>          One line description of <script_name_1>
-> <script_name_2>          One line description of <script_name_2>
-> <script_name_3>          One line description of <script_name_3>
...
```